# Oracle® GoldenGate

Oracle Times Ten Installation and Setup Guide

version 10.4

October 2009



**Oracle® GoldenGate** Oracle Times Ten Installation and Setup Guide, version 10.4

Copyright © 1995, 2009 Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

# Contents


**Chapter 1 System requirements and preinstallation instructions** . . . 3

Overview of GoldenGate for Oracle TimesTen . . . 3
Supported platforms . . . 3
Operating system requirements . . . 3
Database requirements . . . 5
Non-supported items . . . 5
Supported and non-supported object names . . . 5
Object names and owners . . . 5
Case sensitivity . . . 5
Supported characters . . . 6
Non-supported characters . . . 7

**Chapter 2 Installing GoldenGate** . . . 8

Installation overview . . . 8
Upgrades . . . 8
New installations . . . 8
Downloading GoldenGate . . . 8
Setting library paths for dynamic builds on UNIX systems . . . 9
Installing GoldenGate on Linux and UNIX . . . 10
Installing the GoldenGate files . . . 10
Configuring Manager and other processes . . . 11
Installing GoldenGate on Windows and Windows Cluster . . . 11
Obtaining the Microsoft redistributable package . . . 11
Installing GoldenGate into a Windows Cluster . . . 11
Installing the GoldenGate files . . . 11
Specifying a custom Manager name . . . 12
Installing Manager as a Windows service . . . 12
Adding GoldenGate as a Windows cluster resource . . . 13
Configuring Manager and other processes . . . 17

**Chapter 3 Uninstalling GoldenGate** . . . 18

Uninstalling GoldenGate from UNIX . . . 18

Uninstalling GoldenGate from Windows (non-cluster) . . . . . 18
Uninstalling GoldenGate from Windows Cluster . . . . . 19

**Appendix 1 GoldenGate installed components** . . . . . 20

GoldenGate Programs and Utilities . . . . . 20
GoldenGate subdirectories . . . . . 22
Other GoldenGate files . . . . . 24
GoldenGate checkpoint table . . . . . 28

**Index** . . . . . 29

CHAPTER 1

# System requirements and preinstallation instructions

## Overview of GoldenGate for Oracle TimesTen

GoldenGate for Oracle Times Ten supports the delivery of data from other types of databases to a TimesTen database. High-speed GoldenGate replication can be used to refresh a TimesTen cache environment with minimal latency. In addition, with its heterogeneous support, GoldenGate enables the TimesTen data store to be used as a data integration point for other data sources.

GoldenGate supports the mapping, filtering, and manipulation of data from other sources to the TimesTen database. GoldenGate does not support the extraction of data from TimesTen to other TimesTen data stores or to other kinds of databases.

## Supported platforms

Oracle TimesTen on 7.0.4 or later

To find out which GoldenGate builds are available for a specific combination of database version and operating system, go to http://support.goldengate.com. A valid user name and password are required to enter this site.

## Operating system requirements

### *Memory requirements*

The amount of memory that is required for GoldenGate depends on the number of concurrent processes that will be running.

- The GoldenGate GGSCI command interface fully supports up to 300 concurrent Replicat processes per instance of GoldenGate. An instance of GoldenGate equates to one Manager process, which is the main controller process.
- Each Replicat process needs approximately 25-55 MB of memory, or more depending on the size of the transactions and the number of concurrent transactions.

### *Disk requirements*

- Assign the following free disk space:

- 50 MB for the GoldenGate installation files. This includes space for the compressed download file and space for the uncompressed files. You can delete the download file after the installation is complete.
- 40 MB for the working directories and binaries for each instance of GoldenGate that you are installing on the system. For example, to install two builds of GoldenGate into two separate directories, allocate 80 MB of space.
- Additional disk space on any system that hosts GoldenGate trails, which contain the working data. The space that is consumed by the trails varies, depending on the volume of data that will be processed. A good starting point is 1 GB.
- To install GoldenGate into a cluster environment, install the GoldenGate binaries and files on a shared file system that is available to all cluster nodes.

#### *TCP/IP*

- Configure the system to use TCP/IP services, including DNS.
- Configure the network with the host names or IP addresses of all systems that will be hosting GoldenGate processes and to which GoldenGate will be connecting. Host names are easier to use.
- GoldenGate requires the following unreserved and unrestricted TCP/IP ports:
  - One port for communication between the Manager process and other GoldenGate processes.
  - A range of ports for local GoldenGate communications: can be the default range starting at port 7840 or a customized range of up to 256 other ports.
- Keep a record of the ports you assigned to GoldenGate. You will specify them with parameters when configuring the Manager process.
- Configure your firewalls to accept connections through the GoldenGate ports.
- If possible, grant unrestricted FTP access to GoldenGate for transfers of data, parameters, and reports between source and target systems. Otherwise, provide for another transfer method. A secure transfer method is also required to resolve support cases.
- If possible, provide a connection between your source and target systems and a site where files can be staged for transfer to and from the GoldenGate Software FTP Support Site (ftp://support.goldengate.com).

#### *Operating system privileges*

- To install on UNIX, the user installing GoldenGate must have read and write privileges on the GoldenGate installation directory.
- The GoldenGate processes require an operating system user that has privileges to read, write, and delete files and subdirectories in the GoldenGate directory. In addition, the user for the Manager process requires privileges to control GoldenGate processes.
- It is recommended that these operating system users be dedicated to GoldenGate. Sensitive information might be available to anyone running a GoldenGate process.

#### *Itanium requirements*

To install GoldenGate on a Microsoft Itanium system, the vcredist_IA64.exe runtime library package must be installed. You can download this package from the Microsoft website. This

package includes VisualStudio DLLs necessary for GoldenGate to operate on the Itanium platform. If these libraries are not installed, GoldenGate generates the following error.

```
"The application failed to initialize properly (0xc0150002). Click on Ok
to terminate the application.
```

#### *Third-party programs*

- Before installing GoldenGate on a Windows system, install and configure the Microsoft Visual C ++ 2005 SP1 Redistributable Package. **Make certain it is the SP1 version of this package, and make certain the get the right bit version for your server**. This package installs runtime components of Visual C++ Libraries. For more information, and to download this package, go to http://www.microsoft.com.
- GoldenGate fully supports virtual machine environments created with any virtualization software on any platform. When installing GoldenGate into a virtual machine environment, select a GoldenGate build that matches the database and the operating system of the virtual machine, not the host system.

## Database requirements

#### *Database user*

- Create a database user that is dedicated to GoldenGate. It can be the same user for all of the GoldenGate processes that must connect to a database:
  - Replicat (target database)
  - DEFGEN (source or target database)
- To preserve the security of your data, and to monitor GoldenGate processing accurately, do not permit other users, applications, or processes to log on or operate as the GoldenGate database user.
- Keep a record of the database users. They are required in the USERID parameter.

## Non-supported items

- Extraction of DML operations
- Extraction or replication of DDL (data definition language) operations

## Supported and non-supported object names

### Object names and owners

Source and target object names must be fully qualified in GoldenGate parameter files, as in fin.emp.

### Case sensitivity

GoldenGate converts all names to upper case.

## Supported characters

GoldenGate supports alphanumeric characters in object names and the column names of key columns and non-key columns. GoldenGate also supports the following non-alphanumeric characters in columns that are not being used by GoldenGate as a key.

**Table 1 Supported non-alphanumeric characters in object names and non-key column names[1]**

| Character | Description |
|---|---|
| ~ | Tilde |
| < > | Greater-than and less-than symbols |
| / | Forward slash |
| \ | Backward slash |
| ! | Exclamation point |
| @ | At symbol |
| # | Pound symbol |
| $ | Dollar symbol |
| % | Percent symbol |
| ^ | Carot symbol |
| ( ) | Open and close parentheses |
| _ | Underscore |
| - | Dash |
| + | Plus sign |
| = | Equal symbol |
| \| | Pipe |
| [ ] | Begin and end brackets |
| { } | Begin and end curly brackets (braces) |

[1] The type of key that is being used by GoldenGate depends on the definition of a given table and whether there are any overrides by means of a KEYCOLS clause. GoldenGate will use a primary key, if available, or a unique key/index (selection is dependent on the database). In the absence of those definitions, all columns of the table are used, but a KEYCOLS clause overrides all existing key types. For columns that are being used by GoldenGate as a key, the characters in the names must be valid for inclusion in a WHERE clause. This list is all-inclusive; a given database platform may or may not support all listed characters.

### Non-supported characters

GoldenGate does not support the following characters in object or column names:

**Table 2 Non-supported characters in object and column names**[1]

| Character | Description |
|---|---|
| & | Ampersand |
| * | Asterisk |
| ? | Question mark |
| : | Colon |
| ; | Semi-colon |
| , | Comma |
| ‘ ’ | Single quotes |
| “ ” | Double quotes |
| ‘ | Accent mark (Diacritical mark) |
| . | Period |
| | Space |

[1] This list is all-inclusive; a given database platform may or may not support all listed characters.

CHAPTER 2

# Installing GoldenGate

## Installation overview

These instructions are for installing GoldenGate for the first time. Installing GoldenGate installs all of the components required to run and manage GoldenGate processing (exclusive of any components required from other vendors, such as drivers or libraries) and it installs the GoldenGate utilities. The installation process takes a short amount of time.

### Upgrades

To upgrade GoldenGate from one version to another, follow the instructions on the GoldenGate support site at http://download.oracle.com/docs/cd/E15881_01/index.htm.

### New installations

To install GoldenGate for the first time, the following steps are required:

- Downloading GoldenGate
- Setting library paths for dynamic builds
- Installing the software

> **NOTE** Before proceeding, make certain that you have reviewed the System Requirements.

## Downloading GoldenGate

1. Navigate to http://edelivery.oracle.com.
2. Select a language.
3. Click **Continue**.
4. Fill in the **Export Validation** form and check the box to agree to the license agreement.
5. Click **Continue**.
6. Select the **Oracle Fusion Middleware** Product Pack, and select the platform on which you will be installing the GoldenGate software.
7. Click **Go**. A list of Oracle Fusion Middleware products for the selected platform is displayed.
8. Select the appropriate Oracle GoldenGate Media Pack.

9. Click **Continue**. The Media Pack contents are displayed, including software builds and documentation.
10. Click **Download** next to each desired component, and follow the automatic download process to transfer the mediapack.zip file to your system.

## Setting library paths for dynamic builds on UNIX systems

As of version 10, GoldenGate uses shared libraries. When installing GoldenGate on a UNIX system, the following must be true *before running GGSCI or any GoldenGate process*.

1. Make certain that the database libraries are added to the system's shared-library environment variables. This procedure is usually performed at database installation time. Consult your Database Administrator if you have any questions.
2. If you will be running a GoldenGate program from outside the GoldenGate installation directory on a UNIX system:
   - (Optional) Add the GoldenGate installation directory to the PATH environment variable.
   - (Required) Add the GoldenGate installation directory to the shared-libraries environment variable.

   For example, given a GoldenGate installation directory of /ggs/10.0, the second command in the following table requires these variables to be set:

| Command | Requires GG libraries in environment variable? |
|---|---|
| $ ggs/10.0 > ./ggsci | No |
| $ ggs > ./10.0/ggsci | Yes |

**To set the variables in Korn shell**

```
PATH=<installation directory>:$PATH
export PATH
<shared libraries variable>=<absolute path of installation directory>:$<shared libraries variable>
export <shared libraries variable>
```

**To set the variables in Bourne shell**

```
export PATH=<installation directory>:$PATH
export <shared libraries variable>=<absolute path of installation directory>:$<shared libraries variable>
```

**To set the variables in C shell**

```
setenv PATH <installation directory>:$PATH
setenv <shared libraries variable> <absolute path of installation directory>:$<shared libraries variable>
```

**Where:** <shared libraries variable> is one of the following:

**UNIX/Linux library path variables per platform**

| Platform[1] | Environment variable |
|---|---|
| ◆ IBM AIX<br>◆ IBM z/OS | LIBPATH |
| HP-UX | SHLIB_PATH |
| ◆ Sun Solaris<br>◆ HP Tru64 (OSF/1)<br>◆ LINUX | LD_LIBRARY_PATH |

[1] A specific platform may or may not be supported by GoldenGate for your database. See the Systems Requirements for supported platforms.

**Example** `export LD_LIBRARY_PATH=/ggs/10.0:$LD_LIBRARY_PATH`

**NOTE** To view the libraries that are required by a GoldenGate process, use the ldd <process> shell command before starting the process. This command also shows an error message for any that are missing.

# Installing GoldenGate on Linux and UNIX

## Installing the GoldenGate files

1. Extract the Oracle GoldenGate mediapack.zip file on a Windows system by using WinZip or an equivalent compression product. This produces a UNIX .tar file.
2. FTP the .tar file in binary mode to the UNIX system and directory where you want GoldenGate to be installed.
3. Extract the .tar file. The GoldenGate files are extracted into the current directory.

   ```
   tar -xvf <filename>.tar
   ```

4. Run the command shell and change directories to the new GoldenGate directory.
5. From the GoldenGate directory, run the GGSCI program.

   ```
   GGSCI
   ```

6. In GGSCI, issue the following command to create the GoldenGate working directories.

   ```
   CREATE SUBDIRS
   ```

7. Issue the following command to exit GGSCI.

   ```
   EXIT
   ```

### Configuring Manager and other processes

- To use GoldenGate, you must configure the Manager process. You must specify a TCP/IP port for Manager to use, and you can specify optional parameters that control dynamic port assignments, trail file maintenance, and other properties.
- To begin using GoldenGate, you need to create and configure at least one Replicat group. Your instructions for these groups determine which data to replicate, and how that data is processed.
- To configure these processes, and to customize GoldenGate, see the *GoldenGate for Windows and UNIX Administrator Guide*.

## Installing GoldenGate on Windows and Windows Cluster

### Obtaining the Microsoft redistributable package

- Before installing GoldenGate on a Windows system, install and configure the Microsoft Visual C ++ 2005 SP1 Redistributable Package. **Make certain it is the SP1 version of this package, and make certain the get the right bit version for your server**. This package installs runtime components of Visual C++ Libraries. For more information, and to download this package, go to http://www.microsoft.com.

### Installing GoldenGate into a Windows Cluster

1. Log into one of the nodes in the cluster.
2. For the GoldenGate installation location, choose a drive that is a resource within the same cluster group that contains the database instance.
3. Ensure that this group is owned by the cluster node that you are logging into.
4. Install GoldenGate according to the following instructions.

### Installing the GoldenGate files

1. Unzip the downloaded file(s) by using WinZip or an equivalent compression product.
2. Move the files in binary mode to a folder on the drive where you want to install GoldenGate. *Do not* install GoldenGate into a folder that contains spaces in its name, for example "GoldenGate Software." GoldenGate relies on path names, but the operating system does not support path names that contain spaces, whether or not they are within quotes.
3. From the GoldenGate folder, run the GGSCI program.

   ```
   GGSCI
   ```

4. In GGSCI, issue the following command to create the GoldenGate working directories.

   ```
   CREATE SUBDIRS
   ```

5. Issue the following command to exit GGSCI.

   ```
   EXIT
   ```

## Specifying a custom Manager name

You must specify a custom name for the Manager process if either of the following is true:

- you want to use a name for Manager other than the default of GGSMGR.
- there will be multiple Manager processes running as Windows services on this system, such as one for the GoldenGate replication software and one for GoldenGate Veridata. Each Manager on a system must have a unique name. Before proceeding further, verify the names of any local Manager services.

#### To specify a custom Manager name

1. From the directory that contains the Manager program, run GGSCI.
2. Issue the following command.

   ```
   EDIT PARAMS ./GLOBALS
   ```

3. In the file, add the following line, where <name> is a one-word name for the Manager service.

   ```
   MGRSERVNAME <name>
   ```

4. Save the file. The file is saved automatically with the name GLOBALS, *without a file extension*. Do not move this file. It is referenced during installation of the Windows service and during data processing.

## Installing Manager as a Windows service

By default, Manager is not installed as a service and can be run by a local or domain account. However, when run this way, Manager will stop when the user logs out. When you install Manager as a service, you can operate it independently of user connections, and you can configure it to start manually or at system start-up. Installing Manager as a service is required on a Windows Cluster, but optional otherwise.

#### To install Manager as a Windows service

1. (Recommended) Log on as the system administrator.
2. Click **Start** > **Run**, and type **cmd** in the **Run** dialog box.
3. From the directory that contains the Manager program that you are installing as a service, run the **install** program with the following syntax:

   ```
   install <option> [...]
   ```

**Where:** <option> is one of the following:

**Table 3 INSTALL options**

| Option | Description |
|---|---|
| ADDEVENTS | Adds GoldenGate events to the Windows Event Manager. By default, GoldenGate errors are generic. To produce more specific error content, copy the following files from the GoldenGate installation directory to the SYSTEM32 directory.<br>category.dll<br>ggsmsg.dll |
| ADDSERVICE | Adds Manager as a service by the name specified in the GLOBALS file, if one exists, or by the default of GGSMGR. ADDSERVICE configures the service to run as the Local System account, the standard for most Windows applications because the service can be run independently of user logins and password changes. To run Manager as a specific account, use the USER and PASSWORD options.[1]<br>The service is installed to start at system boot time (see AUTOSTART). To start it after installation, either reboot the system, or start the service manually from the Services applet of the Control Panel. |
| AUTOSTART | Specifies that the service created with ADDSERVICE is to be started at system boot time. This is the default unless MANUALSTART is used. |
| MANUALSTART | Specifies that the service created with ADDSERVICE is to be started manually through GGSCI, a script, or the Services applet of the Control Panel. The default is AUTOSTART. |
| USER <name> | Specifies a domain user account for executing Manager. For <name>, include the domain name, a backward slash, and the user name, for example HEADQT\GGSMGR.<br>By default, the Manager service is installed to use the Local System account. |
| PASSWORD <password> | Specifies the password for the user specified with USER. |


[1] A user account can be changed by selecting the Properties action from the Services applet of the Windows Control Panel.

## Adding GoldenGate as a Windows cluster resource


If you installed GoldenGate into a cluster, follow these instructions to establish GoldenGate as a cluster resource and configure the Manager service correctly on all nodes.

1. In the Cluster Administrator, select **File>New>Resource**.

2. In the New Resource dialog box, provide a descriptive name for the GoldenGate Manager (need not be its actual name). For Resource Type, select Generic Service. For Group, select the group that contains the database instance to which GoldenGate will connect.





3. Click **Next**.
4. In the Possible Owners dialog box, select the nodes on which GoldenGate will run.





5. Click **Next**.
6. In the GGS Manager Service Properties dialog box, click the Dependencies tab, and add the following to the Resource dependencies list:
   - The database resource group (in this example, it is "Database")


- The disk resource containing the GoldenGate directory
- The disk resource containing the database transaction log files
- The disk resource containing the database transaction log backup files




7. Click **Apply**, then **OK**.
8. In the Generic Service Parameters dialog box, type either the default Manager service name of GGSMGR or, if applicable, the custom name specified in the GLOBALS file.



9. Click **Next**.
10. Click **Finish** to exit the wizard.
11. In the Cluster Administrator tree, right-click the Manager resource and select Properties.
12. Click the Advanced tab, and deselect Affect the Group. This is a recommendation, but you can configure it as needed for your environment.




13. Click **Apply**.
14. Bring the cluster resource online to verify that it was installed correctly.
15. Take the resource offline again.
16. Move the group to the next node in the cluster. When the group has been successfully moved to the second node, the Manager resource should still be offline.
17. Log onto the second node.
18. Install GoldenGate Manager as a service on this node by running the **install** program as you did on the previous node. If you created a custom name for Manager in the GLOBALS file, that name will be used.
19. Bring the resource online to verify that it is running correctly on this node.
20. Repeat steps 18 through 22 for each additional node in the cluster.

## Configuring Manager and other processes

- To use GoldenGate, you must configure the Manager process. You must specify a TCP/IP port for Manager to use, and you can specify optional parameters that control dynamic port assignments, trail file maintenance, and other properties.
- To begin using GoldenGate, you need to create and configure at least one Replicat group. Your instructions for these groups determine which data to replicate, and how that data is processed.
- To configure these processes, and to customize GoldenGate, see the *GoldenGate for Windows and UNIX Administrator Guide*.

CHAPTER 3

# Uninstalling GoldenGate

This procedure assumes that you no longer need the data in the GoldenGate trails, and that you no longer need to preserve the current GoldenGate environment. To preserve your current environment and data, make a backup of the GoldenGate directory and all subdirectories before starting this procedure.

## Uninstalling GoldenGate from UNIX

1. Run the command shell.
2. (Suggested) Log on as the system administrator, or as a user with permission to issue GoldenGate commands, and to delete files and directories from the operating system.
3. Change directories to the GoldenGate installation directory.
4. Run GGSCI.
5. Stop all GoldenGate processes.
6. Stop the Manager process.
7. Exit GGSCI.
8. Remove the GoldenGate files by removing the installation directory.
9. Drop any GoldenGate-related objects from the database as needed.

## Uninstalling GoldenGate from Windows (non-cluster)

1. (Suggested) Log on as the system administrator, or as a user with permission to issue GoldenGate commands, and to delete files and directories from the operating system.
2. From the GoldenGate installation folder, run GGSCI.
3. Stop all GoldenGate processes.
4. Stop the Manager program or service.
5. Exit GGSCI.
6. Click **Start** > **Run**, and type cmd in the **Run** dialog box.
7. Change directories to the GoldenGate installation directory.

8. Run the install program using the following syntax.

   ```
   install deleteevents deleteservice
   ```

   This command deletes GoldenGate events from being reported to the Windows Event Manager and removes the GoldenGate Manager service.
9. Delete the CATEGORY.DLL and GGSMSG.DLL files from the Windows SYSTEM32 folder.
10. Delete the GoldenGate installation folder.
11. Drop any GoldenGate-related objects from the database as needed.

## Uninstalling GoldenGate from Windows Cluster

1. Working from the node in the cluster that owns the cluster group containing the Manager resource, run GGSCI and then stop any Extract and Replicat processes that are still running.
2. Use the Cluster Administrator tool to take the Manager resource offline.
3. Right click the resource and select **Delete** to remove it.
4. Run the install program using the following syntax.

   ```
   install deleteevents deleteservice
   ```

   This command deletes GoldenGate events from being reported to the Windows Event Manager and removes the GoldenGate Manager service.
5. Delete the CATEGORY.DLL and GGSMSG.DLL files from the Windows SYSTEM32 folder.
6. Move the cluster group to the next node in the cluster, and repeat from step 4.
7. Delete the GoldenGate installation folder.
8. Drop any GoldenGate-related objects from the database as needed.

APPENDIX 1

# GoldenGate installed components

This appendix describes the programs, directories, and other components created or used by the GoldenGate software in the GoldenGate installation directory. Additional files not listed here might be installed on certain platforms. Files listed here might not be installed on every platform.

## GoldenGate Programs and Utilities

This section describes programs installed in the root GoldenGate installation directory.

**Table 4 Programs and utilities**

| Program | Description |
|---|---|
| cobgen | Generates source definitions based on COBOL layouts. Used for GoldenGate for Datawise on Stratus. |
| convchk | Converts checkpoint files to a newer version. |
| ddlcob | Generates target DDL table creation statements based on COBOL layouts. Used for GoldenGate for Datawise on Stratus. |
| ddlgen | Generates target database table definitions based on source database DDL. |
| defgen | Generates data definitions and is referenced by GoldenGate processes when source and target tables have dissimilar definitions. |
| emsclnt | Sends event messages created by Collector and Replicat on Windows or UNIX systems to EMS on NonStop systems. |
| extract | Performs extraction from database tables or transaction logs or receives transaction data from a vendor access module. |
| ggmxinstall | GoldenGate installation script for SQL/MX. |
| ggsci | User interface to GoldenGate for issuing commands and managing parameter files. |

**Table 4 Programs and utilities (continued)**

| Program | Description |
|---|---|
| ggsmgr.jcl<br>ggsmgr.proc<br>ggsmgrst.jcl<br>ggsmgrst.proc | Start the GoldenGate Manager process from a batch job or the operator console on a z/OS system. |
| install | Installs GoldenGate as a Windows service and provides other Windows-based service options. |
| keygen | Generates data-encryption keys. |
| logdump | A utility for viewing and saving information stored in extract trails or files. |
| mgr | (Manager) Control process for resource management, control and monitoring of GoldenGate processes, reporting, and routing of requests through the GGSCI interface. |
| replicat | Applies data to target database tables. |
| reverse | A utility that reverses the order of transactional operations, so that Replicat can be used to back out changes from target tables, restoring them to a previous state. |
| server | The Collector process, an Extract TCP/IP server collector that writes data to remote trails. |
| triggen | Generates scripts that create the GoldenGate log table and logging triggers to support the trigger-based extraction method. |
| vamserv | Started by Extract to read the TMF audit trails generated by TMF-enabled applications using the NonStop SQL/MX database. |

## GoldenGate subdirectories

This section describes the subdirectories of the GoldenGate installation directory and their contents.

**Table 5 Subdirectories**

| Directory | Description |
|---|---|
| dirchk | Contains the checkpoint files created by Extract and Replicat processes, which store current read and write positions to support data accuracy and fault tolerance. Written in internal GoldenGate format.<br>File name format is <group name><sequence number>.<ext> where <sequence number> is a sequential number appended to aged files and <ext> is either cpe for Extract checkpoint files or cpr for Replicat checkpoint files.<br>Do not edit these files.<br>Examples:<br>ext1.cpe<br>rep1.cpr |
| dirdat | The default location for GoldenGate trail files and extract files created by Extract processes to store records of extracted data for further processing, either by the Replicat process or another application or utility. Written in internal GoldenGate format.<br>File name format is a user-defined two-character prefix followed by either a six-digit sequence number (trail files) or the user-defined name of the associated Extract process group (extract files).<br>Do not edit these files.<br>Examples:<br>rt000001<br>finance |
| dirdef | The default location for data definitions files created by the DEFGEN utility to contain source or target data definitions used in a heterogeneous synchronization environment. Written in external ASCII. File name format is a user-defined name specified in the DEFGEN parameter file.<br>These files may be edited to add definitions for newly created tables. If you are unsure of how to edit a definitions file, contact GoldenGate technical support.<br>Example:<br>defs.dat |
| dirout | This directory is not used any more. |

**Table 5 Subdirectories (continued)**

| Directory | Description |
|---|---|
| dirpcs | Default location for status files. File name format is <group>.<extension> where <group> is the name of the group and <extension> is either pce (Extract), pcr (Replicat), or pcm (Manager).<br>These files are only created while a process is running. The file shows the program name, the process name, the port number, and the process ID.<br>Do not edit these files.<br>Examples:<br>mgr.pcm<br>ext.pce |
| dirprm | The default location for GoldenGate parameter files created by GoldenGate users to store run-time parameters for GoldenGate process groups or utilities. Written in external ASCII format. File name format is <group name/user-defined name>.prm or mgr.prm.<br>These files may be edited to change GoldenGate parameter values. They can be edited directly from a text editor or by using the EDIT PARAMS command in GGSCI.<br>Examples:<br>defgen.prm<br>finance.prm |
| dirrec | Not used by GoldenGate. |
| dirrpt | The default location for process report files created by Extract, Replicat, and Manager processes to report statistical information relating to a processing run. Written in external ASCII format.<br>File name format is <group name><sequence number>.rpt where <sequence number> is a sequential number appended to aged files.<br>Do not edit these files.<br>Examples:<br>fin2.rpt<br>mgr4.rpt |
| dirsql | The default location for scripts created by the TRIGGEN utility to contain SQL syntax for creating GoldenGate logging triggers and GoldenGate log tables. Written in external ASCII format.<br>File name format is a user-defined name or the defaults of GGSLOG (table-creation script) or the table name (trigger-creation script), with the extension of .sql.<br>These scripts can be edited if needed.<br>Examples:<br>ggslog.sql<br>account.sql |

**Table 5 Subdirectories (continued)**

| Directory | Description |
|---|---|
| dirtmp | The default location for storing large transactions when the size exceeds the allocated memory size. Do not edit these files. |
| dirver | A GoldenGate Veridata directory. Not used unless this software is installed in the GoldenGate location. |

## Other GoldenGate files

This section describes other files, templates, and other objects created or installed in the root GoldenGate installation directory.

**Table 6 Other files**

| Component | Description |
|---|---|
| bcpfmt.tpl | Template for use with Replicat when creating a run file for the Microsoft BCP/DTS bulk-load utility. |
| blowfish.txt | Blowfish encryption software license agreement. |
| category.dll | Windows dynamic link library used by the INSTALL program. |
| chkpt_<db>_create.sql | Script that creates a checkpoint table in the local database. A different script is installed for each database type. |
| db2cntl.tpl | Template for use with Replicat when creating a control file for the IBM LOADUTIL bulk-load utility. |
| ddl_access.tpl | Template used by the DDLGEN utility to convert source DDL to Microsoft Access DDL. |
| ddl_cleartrace.sql | Script that removes the DDL trace file. (Oracle installations) |
| ddl_db2.tpl | Template used by the DDLGEN utility to convert source DDL to DB2 DDL (Linux, UNIX, Windows). |
| ddl_db2_os390.tpl | Template used by the DDLGEN utility to convert source DDL to DB2 DDL (z/OS systems). |
| ddl_disable.sql | Script that disables the GoldenGate DDL trigger. (Oracle installations) |
| ddl_enable.sql | Script that enables the GoldenGate DDL trigger. (Oracle installations) |

**Table 6 Other files (continued)**

| Component | Description |
|---|---|
| ddl_informix.tpl | Template used by the DDLGEN utility to convert source DDL to Informix DDL. |
| ddl_mss.tpl | Template used by the DDLGEN utility to convert source DDL to SQL Server DDL. |
| ddl_mysql.tpl | Template used by the DDLGEN utility to convert source DDL to MySQL DDL. |
| ddl_nssql.tpl | Template used by the DDLGEN utility to convert source DDL to NonStop SQL DDL. |
| ddl_ora9.sql | A script that gets tablespace information from an Oracle 9 database. |
| ddl_ora10.sql | A script that disables the Oracle recyclebin and gets tablespace information from an Oracle 10 database. |
| ddl_oracle.tpl | Template used by the DDLGEN utility to convert source DDL to Oracle DDL. |
| ddl_pin.sql | Script that pins DDL tracing, the DDL package, and the DDL trigger for performance improvements. (Oracle installations) |
| ddl_remove.sql | Script that removes the DDL extraction trigger and package. (Oracle installations) |
| ddl_setup.sql | Script that installs the GoldenGate DDL extraction and replication objects. (Oracle installations) |
| ddl_sqlmx.tpl | Template used by the DDLGEN utility to convert Tandem Enscribe DDL to NonStop SQL/MX DDL. |
| ddl_status.sql | Script that verifies whether or not each object created by the GoldenGate DDL support feature exists and is functioning properly. (Oracle installations) |
| ddl_sybase.tpl | Template used by the DDLGEN utility to convert source DDL to Sybase DDL. |
| ddl_tandem.tpl | Template used by the DDLGEN utility to convert source DDL to NonStop SQL DDL. |
| ddl_tracelevel.sql | Script that sets the level of tracing for the DDL support feature. (Oracle installations) |
| debug files | Debug text files that may be present if tracing was turned on. |

**Table 6 Other files (continued)**

| Component | Description |
|---|---|
| demo_<db>_create.sql | Script that creates demonstration tables in the database associated with the GoldenGate installation. |
| demo_<db>_insert.sql | Script that inserts initial test data into the demonstration tables. |
| demo_<db>_misc.sql | Script that simulates transaction activity on the demonstration tables. |
| ENCKEYS | User-created file that stores encryption keys. Written in external ASCII format. |
| exitdemo.c | User exit example. |
| ggmessage.dat | Data file that contains error, informational, and warning messages that are returned by the GoldenGate processes. The version of this file is checked upon process startup and must be identical to that of the process in order for the process to operate. |
| ggserr.log | File that logs processing events, messages, errors, and warnings generated by GoldenGate. |
| ggsmsg.dll | Windows dynamic link library used by the INSTALL program. |
| GLOBALS | User-created file that stores parameters applying to the GoldenGate instance as a whole. |
| help.txt | Help file for the GGSCI command interface. |
| LGPL.txt | Lesser General Public License statement. Applies to free libraries from the Free Software Foundation. |
| libodbc.so | ODBC file for Ingres 2.6 on Unix. |
| libodbc.txt | License agreement for libodbc.so. |
| libxml2.dll | Windows dynamic link library containing the XML library for GoldenGate's XML procedures. |
| libxml2.txt | License agreement for libxml2.dll. |
| marker.hist | File created by Replicat if markers were passed from a NonStop source system. |
| marker_remove.sql | Script that removes the DDL marker table. (Oracle installations) |
| marker_setup.sql | Script that installs the GoldenGate DDL marker table. (Oracle installations) |

**Table 6 Other files (continued)**

| Component | Description |
|---|---|
| marker_status.sql | Script that confirms successful installation of the DDL marker table. (Oracle installations) |
| odbcinst.ini | Ingres 2.6 on Unix ODBC configuration file. |
| params.sql | Script that contains configurable parameters for DDL support. (Oracle installations) |
| pthread-win32.txt | License agreement for pthread-VC.dll. |
| pthread-VC.dll | POSIX threads library for Microsoft Windows. |
| role_setup.sql | Script that creates the database role necessary for GoldenGate DDL support. (Oracle installations) |
| sampleodbc.ini | Sample ODBC file for Ingres 2.6 on UNIX. |
| sqlldr.tpl | Template for use with Replicat when creating a control file for the Oracle SQL*Loader bulk-load utility. |
| start.prm<br>stop.prm | z/OS paramlib members to start and stop the Manager process. |
| startmgr<br>stopmgr | z/OS Unix System Services scripts to start the Manager process from GGSCI. |
| startmgrcom<br>stopmgrcom | z/OS system input command for the Manager process. |
| tcperrs | File containing user-defined instructions for responding to TCP/IP errors. |
| usrdecs.h | Include file for user exit API. |
| zlib.txt | License agreement for zlib compression library. |

## GoldenGate checkpoint table

When database checkpoints are being used, GoldenGate creates a checkpoint table with a user-defined name in the database upon execution of the ADD CHECKPOINTTABLE command, or a user can create the table by using the chkpt_<db>_create.sql script, where <db> is the type of database.

Do not change the names or attributes of the columns in this table. You can change table storage attributes as needed.

**Table 7 Checkpoint table definitions**

| Column | Description |
|---|---|
| GROUP_NAME (primary key) | The name of a Replicat group using this table for checkpoints. There can be multiple Replicat groups using the same table. |
| GROUP_KEY (primary key) | A unique identifier that, together with GROUPNAME, uniquely identifies a checkpoint regardless of how many Replicat groups are writing to the same table. |
| SEQNO | The sequence number of the checkpoint file. |
| RBA | The relative byte address of the checkpoint in the file. |
| AUDIT_TS | The timestamp of the checkpoint position in the checkpoint file. |
| CREATE_TS | The date and time when the checkpoint table was created. |
| LAST_UPDATE_TS | The date and time when the checkpoint table was last updated. |
| CURRENT_DIR | The current GoldenGate home directory or folder. |

# Index


## Symbols

**$LD_LIBRARY_PATH variable** 10
**$PATH variable** 9

## A

**ADDEVENTS Windows service option** 13
**ADDSERVICE Windows service option** 13
**AUTOSTART Windows service option** 13

## C

**category.dll** 13
**characters**
  supported in object names 6
**cluster, installing on** 4, 11, 13
**connections, to database** 5
**CREATE SUBDIRS command** 10

## D

**database requirements** 5
**disk requirements** 4
**downloading GoldenGate** 8

## E

**environment variables, setting** 9

## F

**firewall, configuring** 4
**FTP access for GoldenGate** 4

## G

**ggmessage.dat file** 26
**GGSMGR default Manager name** 12
**ggsmsg.dll** 13
**GLOBALS file** 12
**GoldenGate**
  downloading 8
  installed programs and files 20
  installing 8
  uninstalling 18

## I

**installing on**
  Linux and UNIX 10
  Windows 11
**Itanium preinstallation requirements** 4

## K

**key**
  name, supported characters 6

## L

**LIBPATH variable** 10
**libraries, Visual C++** 5, 11
**Linux, installing on** 10

## M

**Manager**
  as Windows service 12
  multiple on same system 12
  name, customizing 12
**MANUALSTART Windows service option** 13
**Memory requirements for GoldenGate** 3
**MGRSERVNAME parameter** 12

**Microsoft Visual C ++ 2005 SP1 Redistributable Package** 5, 11

## N

**name**
non-supported characters in 7
supported characters in 6

## P

**PASSWORD Windows service option** 13
**platforms, supported** 3
**ports, required by GoldenGate** 4
**privileges**
database 5
operating system 4

## R

**removing**
GoldenGate from system 18

## S

**SHLIB_PATH variable** 10
**spaces**
in folder names 11
**subdirectories, creating** 10

## T

**TCP/IP, configuring** 4

## U

**uninstalling GoldenGate** 18
**UNIX, installing on** 10
**USER Windows service option** 13
**user, GoldenGate** 5
**USERID parameter** 5

## V

**VAMSERV program** 21
**vcredist_IA64.exe runtime library** 4
**virtual machine, support for** 5
**Visual C ++ 2005 SP1 Redistributable Package** 5, 11

## W

**Windows, installing on** 11